
ACTIVITY GENERATOR HOW-TO

1 GENERAL

This document provides information about using an activity survey to assign activity patterns to household members and distribute them to activity locations. The synthetically generated activity records for the entire population will serve as input to the **Router**.



1.1 Revision History

| 12/6/2006 | Created by AECOM Consult, Inc. |
|-----------|--------------------------------|
| 3/2/2007 | Revised by AECOM Consult Inc. |
| 9/12/2007 | Revised by AECOM Consult Inc. |
| 4/1/2010 | Revised by RSG Inc. |



1.2 Table of Contents

- 1 General
 - 1.1 Revision History
 - 1.2 Table of Contents
 - 1.3 Type Setting
 - 1.4 Assumptions and Prerequisites
- 2 Activity Generator Overview
- 3 Survey Data Preparation
 - 3.1 Survey Household File
 - 3.2 Survey Population File
 - 3.3 Survey Activity File
 - 3.4 Survey Weights File
- 4 Household Matching
- 5 Location Choice
- 6 Program Execution
- 7 Troubleshooting
- 8 Frequently Asked Questions

1.3 Type Setting

This document uses the following typesetting throughout the text:

Normal Text To indicate normal document text

Program To indicate a program or software such as **TRANSIMS** or **Excel**

Filename To indicate a file such as PopSyn.ct1

[Menu option | Sub-option] To indicate a drop down menu option such as [File | Save]

<Button> To indicate buttons or options on dialog boxes such as <Open>
To indicate a field header name within a data file such as |HHOLD|

CONTROL_KEY To indicate a control key or option within the control file such as

NET_DIRECTORY

1.4 Assumptions and Prerequisites

This document assumes that the user has installed **TRANSIMS 4.0.03** on a **Windows** or **Linux** computer system and understands the basic procedures and terminology for executing **TRANSIMS** programs. Moreover, the user is assumed to have completed the Highway Network Conversion How-To and the Transit Network Conversion How-To case studies to generate the necessary network data files.

The TRANSIMS software and documentation can be downloaded from http://sourceforge.net/projects/transims/files/. Basic TRANSIMS procedures and terminology are addressed in the Installation and Testing How-To.



Text files are used to store the input and output information. A standard text editor such as **Pico**, **TextPad**, or **WordPad** (or any other software that can handle text files) is needed to manipulate the text.

This how-to document uses network information from Alexandria, Virginia, to demonstrate procedures, discuss outcomes, and describe concepts. Sample survey records have been extracted from an activity-based survey conducted in Portland, Oregon.

The Alexandria **TRANSIMS** network may be downloaded to a local hard drive from: http://sourceforge.net/projects/transims/files/ → test data → 4.03a Test Cases → Alexandria_4.0.3a.zip

Unzip the Alexandria data to the following directory depending on the platform used:

• c:\TRANSIMS\Alexandria (Windows)

/home/TRANSIMS/Alexandria (Linux)

The survey folder contains, among other data, information about survey households, persons, and activities. The input files relevant to **ActGen** in this folder are:

- Survey_Activity.txt
- Survey_Household.txt
- Survey_Population.txt
- Survey_Weights.txt

2 ACTIVITY GENERATOR OVERVIEW

The **ActGen** program performs the following tasks:

- Assigns activities to each household member,
- Determines start and end-time of activities over the course of a day,
- Selects a location for each activity, and
- Defines the travel mode used to travel to that location.

Each of these tasks can be accomplished using a variety of methods and user-defined models. This case study focuses on <u>simple models and procedures that demonstrate the process rather</u> than define best practice. Most real-world applications will use more sophisticated procedures.

From the **TRANSIMS** perspective, travel is a means of accomplishing activities at different locations. "Activities" in this context consist of the things people do over the course of a typical day, such as work, shop, attend school, eat, and sleep. The activities can be performed at home or at other locations. Activities performed at home are labeled as "at home" activities, while activities performed outside the home are collectively grouped as "tours". A tour comprises all the activities that take place from the time a person leaves home until the time that person returns home. A person can conduct several tours throughout the day alone or with other household members. A person may also perform one or more sub-tours during a tour. A sub-tour is a series



of activities that start and end at a given location. The work location is often the anchor point for sub-tours. For example, if a person went out to lunch during his work activity, that would be considered a sub-tour that started and ended at the work location.

Some activities are considered flexible or discretionary, while others are fixed or mandatory. Work and school, for example, are likely to be mandatory activities that have fixed start and end times. Shopping activities, on the other hand, are typically flexible, with more variability in location and duration. **TRANSIMS** enables the user to define the time and flexibility constraints for each activity type or purpose. The program considers this information together with the travel time between activity locations when constructing a realistic activity schedule for each household member. If several household members need to coordinate their activities or their travel (for example, to drive a child to school), those constraints are considered.

The **ActGen** program uses a household activity survey to define the activity patterns, activity schedule, and travel modes for each synthetic household member generated by the **PopSyn**. A household type model allows the synthetic household to be matched with a survey household based on household demographic attributes. The activities for each person in the survey household are then assigned to an appropriate person in the synthetic household.

The household activities are allocated to activity locations based on the home location and location choice models. Location choice models are typically defined by activity purpose (work, shopping, etc...) and travel mode (walk, drive, etc...). The default model uses the straight-line distance between potential activity locations and known locations, along with location attraction factors, to select one of the potential locations for the activity. The attraction factors assigned to each activity location can vary by the purpose of the activity. For example, the attraction factors for work activities are likely to include the number of jobs at each location.

To more accurately consider mode-specific travel conditions by time of day in the location selection process, the user can incorporate location choice scripts and zone-to-zone skims by time of day and travel mode. That level of sophistication is, however, beyond the scope of this document. The user is referred to **ActGen** documentation for more information on advanced location choice procedures.

3 SURVEY DATA PREPARATION

The survey data are provided in four files: a household file (<code>Survey_Household.txt</code>), a population file (<code>Survey_Population.txt</code>), an activity file (<code>Survey_Activity.txt</code>), and survey weights file (<code>Survey_Weights.txt</code>). The household file defines the number of persons and vehicles in the household, as well as any additional household attributes needed to define household type and location choice (such as number of workers, income, and area type). The population file includes a data record for each person in the household; these records typically identify the person's age, gender, work status, and other attributes. The activity file includes the sequence of activities performed by each household member over the course of a day. The purpose, start time, end time, travel mode, vehicle number, number of passengers, and location is provided for each activity.



3.1 Survey Household File

Selected records from **Survey_Household.txt** are shown below.

| HHOLD | HHSIZE | WORKERS | VEHICLES | INCOME | HHAGE | NUM_LT5 | NUM_5TO15 | LOCATION |
|--------|--------|---------|----------|--------|-------|---------|-----------|----------|
| 200007 | 1 | 1 | 1 | 14 | 29 | 0 | 0 | 1 |
| 200009 | 1 | 0 | 0 | 1 | 82 | 0 | 0 | 1 |
| 200010 | 2 | 1 | 2 | 11 | 25 | 0 | 0 | 2 |
| 200015 | 1 | 0 | 0 | 14 | 82 | 0 | 0 | 2 |
| 200020 | 1 | 0 | 0 | 2 | 77 | 0 | 0 | 2 |

For example, household 200010, has 2 persons, one of which is a worker, owns 2 vehicles, and belongs to income category 11 (14 categories in total). The location field has no impact on the activity generation process since synthetic households carry are already assigned to an activity location in the **PopSyn** process.

3.2 Survey Population File

Selected records from **Survey_Population.txt** are shown below.

| | | _ | | | |
|--------|--------|-----|--------|------|--------|
| HHOLD | PERSON | AGE | GENDER | WORK | RELATE |
| 200007 | 1 | 29 | 2 | 1 | 1 |
| 200009 | 1 | 82 | 2 | 2 | 1 |
| 200010 | 1 | 25 | 1 | 1 | 1 |
| 200010 | 2 | 28 | 2 | 2 | 1 |
| 200015 | 1 | 82 | 1 | 2 | 1 |
| 200020 | 1 | 77 | 1 | 2 | 1 |

For example, household 200010 has 2 records, one for each person. Person 1 is a 25 years old (|AGE| = 25) male (|GENDER| = 1) who works (|WORK| = 1). Person 2 is a 28 years old (|AGE| = 28) female (|GENDER| = 2) who does not work (|WORK| = 2). |RELATE| is a 1990 US Census acronym that indicates the relationship of a household member to the householder. It has no impact the matching process within **ActGen**.

3.3 Survey Activity File

The activity records for household 200010 are shown below.

| HHOLD | PERSON | ACTIVITY | PURPOSE | PRIORITY | START | END | DURATION | MODE | VEHICLE | LOCATION | PASSENGERS | CONSTRAINT |
|--------|--------|----------|---------|----------|-------|-------|----------|------|---------|----------|------------|------------|
| 200010 | 1 | 1 | 0 | 0 | 0:00 | 10:39 | 10:39 | 1 | 0 | 1 | 0 | 0 |
| 200010 | 1 | 2 | 13 | 0 | 11:10 | 11:25 | 0:15 | 2 | 2 | 2 | 1 | 0 |
| 200010 | 1 | 3 | 12 | 2 | 11:50 | 13:20 | 1:30 | 2 | 2 | 3 | 1 | 0 |
| 200010 | 1 | 4 | 15 | 0 | 13:40 | 14:30 | 0:50 | 2 | 2 | 4 | 1 | 0 |
| 200010 | 1 | 5 | 12 | 0 | 14:45 | 15:00 | 0:15 | 2 | 2 | 5 | 1 | 0 |
| 200010 | 1 | 6 | 0 | 0 | 15:21 | 15:51 | 0:30 | 2 | 2 | 1 | 1 | 0 |
| 200010 | 1 | 7 | 9 | 2 | 16:05 | 22:30 | 6:25 | 2 | 2 | 6 | 1 | 0 |



| 200010 | 1 | 8 | 0 | 0 | 22:45 | 1@3:00 | 4:15 | 8 | 0 | 1 | 1 | 0 |
|--------|---|---|----|---|-------|--------|-------|---|---|---|---|---|
| 200010 | 2 | 1 | 0 | 0 | 0:00 | 10:39 | 10:39 | 1 | 0 | 1 | 0 | 0 |
| 200010 | 2 | 2 | 13 | 0 | 11:10 | 11:25 | 0:15 | 2 | 1 | 2 | 1 | 0 |
| 200010 | 2 | 3 | 12 | 2 | 11:50 | 13:20 | 1:30 | 2 | 1 | 3 | 1 | 0 |
| 200010 | 2 | 4 | 15 | 0 | 13:40 | 14:30 | 0:50 | 2 | 1 | 4 | 1 | 0 |
| 200010 | 2 | 5 | 12 | 0 | 14:45 | 15:00 | 0:15 | 2 | 1 | 5 | 1 | 0 |
| 200010 | 2 | 6 | 0 | 0 | 15:21 | 15:51 | 0:30 | 2 | 1 | 1 | 1 | 0 |
| 200010 | 2 | 7 | 6 | 2 | 16:05 | 16:06 | 0:01 | 2 | 1 | 6 | 1 | 0 |
| 200010 | 2 | 8 | 0 | 0 | 16:20 | 1@3:00 | 10:40 | 2 | 1 | 1 | 1 | 0 |

The activity purposes can be customized for local needs, with the only restriction being that purpose zero must be home. For this dataset, the following purpose codes are defined:

- 0 Home
- 1 Work
- 2 Shop
- 3 Visit
- 4 Social/Recreation
- 5 Other
- 6 Serve Passenger
- 7 School
- 8 College

The mode codes are defined by **ActGen** as follows:

- 1 Walk
- 2 Drive
- 3 Bus
- 4 Rail
- 5 Park-and-Ride Outbound
- 6 Park-and-Ride Inbound
- 7 Bicycle
- 8 Magic Move (travel with non-household members)
- 9 School Bus
- 10 Two-Person Carpool
- 11 Three-Person Carpool, and
- 12 Four-Person Carpool

The vehicle codes are defined by **ActGen** as follows:

- 0 No auto
- 1 Auto, driver
- 2 Auto, passenger

The passenger codes represent the number of passengers besides the driver. That is a if |Vehicle| = 2 (i.e. Auto, passenger), then $|PASSENGER| \ge 1$.



Location codes have meaning only for a given household. They simply tell the program to change location or to return to a previously defined location. For example, the home location is represented by location code 1. Each time the program finds a "1" in the location field, it returns to the activity location where the household is located.

3.4 Survey Weights File

Selected records from **Survey_Weights.txt** are shown below. For example, household 200007 has a weight of 6.2616564. Similarly, household 200010 has a weight of 4.9028446. These weights are used in the matching process to select a survey household for each synthetic household. Therefore among survey households with the same type, the probability of selecting a survey household is proportional to its survey weight.

| 200007 | 6.2616564 |
|--------|-----------|
| 200009 | 10.073464 |
| 200010 | 4.9028446 |
| 200015 | 3.511354 |
| 200020 | 3.8874022 |
| 200029 | 49.726312 |

4 HOUSEHOLD MATCHING

The activity assignment process starts by matching each synthetic household to a survey household. The characteristics of the household are used to classify the household type. The program then 1) identifies all of the survey households with the same household type, 2) randomly selects one of those households, based on survey weights (<code>Survey_Weights.txt</code>); and 3) assigns its activities to the synthetic household.

Household type codes can be hard coded into the household data files or defined by a household type script. The script uses the same variables defined for the household file such as household size, number of vehicles owned, and number of workers to assign a specific household type code to the household. If the survey household file and the synthetic household file use different variable names, then a separate household type script must be used for each. The following example shows a simple household type script that uses household size and number of workers to define six household types. (A full description of the script syntax options can be found in the **ActGen** User's Guide).

```
IF (Household.PERSONS > 2) THEN
    IF (Household.PERSONS > 3) THEN
        IF (Household.WORKERS == 2) THEN
            RETURN (1)
    ELSE
            RETURN (2)
    ENDIF

ELSE
    IF (Household.WORKERS == 1) THEN
        RETURN (3)
```



```
ELSE

RETURN (4)

ENDIF

ENDIF

ELSE

IF (Household.WORKERS == 1) THEN

RETURN (5)

ELSE

RETURN (6)

ENDIF

ENDIF
```

Given the household type, the **ActGen** randomly selects a household from the survey dataset with the same type. It then gathers the members of the survey household for the person-matching process. The program matches each person in the synthetic household to the most appropriate person in the survey household. This is done using the age, work status, and gender fields in the population files. Each person is first assigned to an age-group, which are defined as follows:

| Age Group | Age Range |
|-----------|-----------|
| 1 | 0–4 |
| 2 | 5–11 |
| 3 | 12–15 |
| 4 | 16-20 |
| 5 | 21-64 |
| 6 | 65+ |

If the survey household does not have a person in the same age-group and with the same worker status and gender as a person in the synthetic household, **ActGen** will attempt to identify the best match by age-group and then work status. The program then retrieves the out-of-home activities from the survey activity file and assigns the activity sequence, activity schedule, and travel mode to the synthetic household member.

5 LOCATION CHOICE

The location choice model uses "anchor" activities to select the location for each activity in a tour. Basically, two previously defined locations, a "previous" and a "subsequent" anchor locations, are needed to select the location for the next activity in the tour. Initially the home location is the only anchor location. The program then scans all the activities included in a tour that starts and ends at home to identify the primary activity or reason for the tour. This is done as follows. If an activity type is identified as an anchor activity in the **ActGen** control file, it will be considered first. If the tour has multiple anchor activities, the program will select the anchor activity with the longest duration as the primary activity. If the tour does not include any anchor activities, the program will consider the activity with the longest duration to be the primary activity for the tour.

Once the primary activity is identified, the program uses the home location as the "previous" and a "subsequent" anchor for locating the primary activity. The time at which the trip leaves home is used to determine the impedance for the outbound trip, and the time at which the trip leaves the primary activity is used to determine the impedance for the return trip. Once the primary



activity is located, the program will locate the activities that take place between home and the primary activity based on the distance to home and the distance to the primary activity location. After the first intermediate stop is located, it becomes the anchor location for locating the next stop on the tour. The process continues until all of the activities are located.

The **ActGen** program provides two ways for estimating the travel conditions for the location choice model. The first is the default method, which uses simple distance calculations as a proxy for travel time. The second is a more advanced approach, which uses zone-to-zone skim files and a modeling script to calculate the probability of selecting a given location. Because skim data can be defined by mode and time of day and then adjusted by household attributes (such as income) or by activity purpose, the skim files can be used to implement very sophisticated location choice models. For this exercise, the default method will be used, in which the utility of selecting a given location *n* is defined by the following equation:

```
 \begin{aligned} Utility_n = & Location\_Weight_n \times Location\_Weight\_Factor_n \times \\ & exp\left[Mode\_Distance\_Factor_{mode} \times (Distance_{Previous \rightarrow n} + Distance_{n \rightarrow subsequent})\right] \end{aligned}
```

where Location_Weight is a user specified additional field in the activity location file representing the relative attractiveness of each activity location. For example, the number of jobs at each activity location can be used to increase the probability of allocating work activities to activity locations that contain more jobs. By default, all location weights are set to 1.0 (i.e., equal weight). The modeler can assign a specific weight to each activity location by introducing additional data fields into the activity location file. Each activity type or purpose can then be assigned to a specific data field. Location_Weight_Factor is an additional location weight factor defined in the control file and used to scale up or down the Location_Weight value defined above. Distance is the computed distance between previous/subsequent anchor locations and a given location n. Mode_Distance_Factor is a scalar parameter defined in the control file and used to adjust the distance based on the network and operation characteristics of each mode.

6 PROGRAM EXECUTION

A sample control file **Alex.2000.Act.ActGen.ct1** for **ActGen** is provided in the Alexandria\control directory. The file can be reviewed and edited using a standard text editor. The file records are listed below.

TITLE Alexandria Activity Generator
DEFAULT_FILE_FORMAT TAB_DELIMITED
PROJECT DIRECTORY ../

#---- Input Files ----

NET_DIRECTORY../networkNET_NODE_TABLENodeNET_LINK_TABLELink

NET_ACTIVITY_LOCATION_TABLE Activity_Location_4
NET_PARKING_TABLE Parking
NET_PROCESS_LINE_TABLE

Parking

NET_PROCESS_LINK_TABLE Process_Link
NET_ZONE_TABLE Zone_Weights



HOUSEHOLD_FILE POPULATION_FILE VEHICLE FILE demand/Alex.2000.Act.Households demand/Alex.2000.Act.Persons demand/Alex.2000.Act.Vehicles

VEHICLE_TYPE_FILE

inputs/Vehicle_Type.txt

HOUSEHOLD TYPE SCRIPT

inputs/Household_Type.txt

SURVEY_HOUSEHOLD_FILE SURVEY_HOUSEHOLD_WEIGHTS SURVEY_POPULATION_FILE SURVEY_ACTIVITY_FILE SURVEY_TYPE_SCRIPT survey/Survey_Household.txt survey/Survey_Weights.txt survey/Survey_Population.txt survey/Survey_Activity.txt survey/Survey Household Type.txt

demand/Alex.2000.Act.Activities

#---- Output File ----

NEW_ACTIVITY_FILE NEW_ACTIVITY_FORMAT NEW PROBLEM FILE

TAB_DELIMITED results/Alex.2000.Act.ActGen_Problems results/Alex.2000.Act.Household_Matches

NEW_HOUSEHOLD_MATCH_FILE

#---- Reports -----

ACTGEN_REPORT_1
ACTGEN_REPORT_2
ACTGEN_REPORT_3
ACTGEN_REPORT_4
ACTGEN_REPORT_5
ACTGEN_REPORT_6
ACTGEN_REPORT_7
ACTGEN_REPORT_8

HOUSEHOLD_TYPE_SUMMARY SURVEY_TYPE_SUMMARY TRIP_LENGTH_SUMMARY TOUR_LENGTH_SUMMARY TRIP_PURPOSE_SUMMARY TOUR_PURPOSE_SUMMARY MODE_LENGTH_SUMMARY MODE_PURPOSE_SUMMARY

#---- Parameters ----

RANDOM_NUMBER_SEED TIME_OF_DAY_FORMAT DISTANCE_CALCULATION AVERAGE_TRAVEL_SPEED ADDITIONAL_TRAVEL_TIME 1234 24_HOUR_CLOCK RIGHT_ANGLE 1.0, 15.0, 10.0 600, 900, 1800

ACTIVITY_PURPOSE_RANGE_1 ACTIVITY_ANCHOR_FLAG_1 SCHEDULE_CONSTRAINT_1 ZONE_WEIGHT_FIELD_1 MODE_DISTANCE_FACTORS_1 1, 7, 8, 9, 11, 17, 18, 19 TRUE FIXED_TIME EMPLOYMENT -0.005, -0.0006, -0.007

ACTIVITY_PURPOSE_RANGE_2 ACTIVITY_ANCHOR_FLAG_2 SCHEDULE_CONSTRAINT_2 ZONE_WEIGHT_FIELD_2 MODE_DISTANCE_FACTORS_2 2..5, 12..15 FALSE NO_CONSTRAINT RETAIL -0.005, -0.0006, -0.007

ACTIVITY_PURPOSE_RANGE_3 ACTIVITY_ANCHOR_FLAG_3 SCHEDULE_CONSTRAINT_3 ZONE_WEIGHT_FIELD_3 6, 16 FALSE PASSENGER EMPLOYMENT



This application includes three activity generation models. The first model is an anchor-based model, in which the start and end times of the activities are fixed. This model includes the following purpose codes: 1 = work, 7 = school, and 8 = college.

The second model is for non-anchor activities with no schedule constraints. These include 2 = shop, 3 = visit, 4 = social/recreation, and 5 = other.

The third model is used for serving a passenger, in which case the constraints of the corresponding passenger's activity control the driver's schedule. For example, the driver's schedule will be constrained if the passenger's activity is time constrained.

Several keys include a list of parameters. The average travel speed, additional travel time, and mode distance factor keys can be defined by travel mode. The order of the parameters corresponds to the order of the mode codes:

- 1. Walk
- 2. Drive
- 3. Bus
- 4. Rail
- 5. Park-and-Ride Outbound
- 6. Park-and-Ride Inbound
- 7. Bicycle
- 8. Magic Move
- 9. School Bus
- 10. Two-Person Carpool
- 11. Three-Person Carpool, and
- 12. Four-Person Carpool

In this case study, mode distance factor values are provided for the first three modes: walk, drive, and bus (MODE_DISTANCE_FACTORS_1 = -0.05, -0.006, -0.07). If the modeler provides data for fewer than 12 modes, the last value provided with the key will be used for all subsequent modes.

Travel time estimates are made to evaluate and adjust the activity schedule. The following calculation is used to determine the mode-specific travel time:

Travel Time = Distance / Average_Travel_Speed + Additional_Travel_Time

By default, the distance value is the straight-line distance between the activity location coordinates. In this case, the <code>DISTANCE_CALCULATION</code> key is set to <code>RIGHT_ANGLE</code> to make the distance equal to the sum of the absolute difference of the X and Y coordinates thus approximating movement on a grid network. The average travel speed and additional travel time are selected based on the travel mode. The additional travel time can be interpreted as the vehicle access and parking time or a time buffer to account for congestion or distance errors.



ActGen can be executed using the batch file included in the Alexandria\batch\ directory:

• Alex.2000.Act.ActGen.bat (Windows)

The printout file **ActGen.prn** will be created by the process, as will be a new activity file in the activity folder. Three reports are requested to summarize the results of the household type model. The end of the printout summarizes the household match and location choice problems.

```
****************
     ActGen - Version 4.0.32
| Copyright (c) 2008 by AECOM Consult
     Wed Apr 14 11:01:20 2010
**************
Control File = ../control/Alex.2000.Act.ActGen.ctl
Report_File = ../control/Alex.2000.Act.ActGen.prn (Create)
Alexandria Activity Generator
Project Directory = ../
Default File Format = TAB_DELIMITED
Network Directory = ../network
Node File = ../network\Node
Zone File = ../network\Zone Weights
Link File = ../network\Link
Parking File = ../network\Parking
Activity Location File = ../network\Activity Location 4
Process Link File = ../network\Process Link
Household File = ../demand/Alex.2000.Act.Households
Population File = ../demand/Alex.2000.Act.Persons
Vehicle Type File = ../inputs/Vehicle Type.txt
Vehicle File = ../demand/Alex.2000.Act. Vehicles
Vehicle File will be Sorted by Vehicle ID
New Activity File = ../demand/Alex.2000.Act.Activities
Time of Day Format = 24_HOUR_CLOCK
Household Type Script = ../inputs/Household_Type.txt
Survey Household File = ../survey/Survey_Household.txt
Survey Household Weights = ../survey/Survey Weights.txt
Survey Type Script = ../survey/Survey Household Type.txt
```

Survey Population File = ../survey/Survey_Population.txt



Survey Activity File = ../survey/Survey_Activity.txt

New Problem File = ../results/Alex.2000.Act.ActGen Problems

New Problem File Format = VERSION3

New Household Match File = ../results/Alex.2000.Act.Household_Matches

Distance Calculation = RIGHT_ANGLE

Average Travel Speed = 1.0, 15.0, 10.0 ... meters/second

Additional Travel Time = 600, 900, 1800 ... seconds

Random Number Seed = 1234

Activity Purpose Range #1 = 1, 7, 8, 9, 11, 17, 18, 19

Activity Anchor Flag #1 = True

Schedule Constraint #1 = FIXED

Zone-Based Method #1 = True

Zone Weight Field Name = EMPLOYMENT, Number = 8

Zone Weight Factor = 1

All Locations have Equal Weight (1.0)

Alexandria Activity Generator

Wed Apr 14 11:01:21 2010 ActGen page 2

The Location Choice Model is Distance-Based

Mode Distance Factors = -0.005, -0.0006, -0.007 ... (*meters)

Activity Purpose Range #2 = 2..5, 12..15

Activity Anchor Flag #2 = False

Schedule Constraint #2 = NONE

Zone-Based Method #2 = True

Zone Weight Field Name = RETAIL, Number = 10

Zone Weight Factor = 1

All Locations have Equal Weight (1.0)

The Location Choice Model is Distance-Based

Mode Distance Factors = -0.005, -0.0006, -0.007 ... (*meters)

Activity Purpose Range #3 = 6, 16

Activity Anchor Flag #3 = False

Schedule Constraint #3 = PASSENGER

Zone-Based Method #3 = True

Zone Weight Field Name = EMPLOYMENT, Number = 8

Zone Weight Factor = 1

All Locations have Equal Weight (1.0)

The Location Choice Model is Distance-Based

Mode Distance Factors = -0.005, -0.0006, -0.007 ... (*meters)

ActGen Reports: 1. HOUSEHOLD_TYPE_SUMMARY

- 2. SURVEY_TYPE_SUMMARY
- 3. TRIP LENGTH SUMMARY
- 4. TOUR_LENGTH_SUMMARY
- 5. TRIP_PURPOSE_SUMMARY
- 6. TOUR_PURPOSE_SUMMARY
- 7. MODE_LENGTH_SUMMARY
- 8. MODE_PURPOSE_SUMMARY



Compiling Household Type Script Compiling Survey Type Script

Number of Survey Household Weights Records = 4562

Number of Survey Household File Records = 4562 Number of Survey Household Types = 20

Alexandria Activity Generator Wed Apr 14 11:01:21 2010 ActGen page 3

Survey Type Summary

Type Households Cumulative Weight Average Weight

| 1 | 478 | 2868.000000 | 6.000000 |
|----|-----|-------------|-----------|
| 2 | 725 | 1957.042897 | 2.699370 |
| 3 | 91 | 27.357374 | 0.300630 |
| 4 | 440 | 4663.693869 | 10.599304 |
| 5 | 413 | 2198.024707 | 5.322094 |
| 6 | 59 | 108.455201 | 1.838224 |
| 7 | 613 | 2653.933515 | 4.329418 |
| 8 | 239 | 160.268989 | 0.670582 |
| 9 | 219 | 2853.240052 | 13.028493 |
| 10 | 341 | 2727.200331 | 7.997655 |
| 11 | 90 | 81.051949 | 0.900577 |
| 12 | 111 | 420.879519 | 3.791707 |
| 13 | 69 | 161.318281 | 2.337946 |
| 14 | 226 | 1158.728404 | 5.127117 |
| 15 | 69 | 350.078244 | 5.073598 |
| 16 | 91 | 195.675987 | 2.150286 |
| 17 | 67 | 247.653180 | 3.696316 |
| 18 | 127 | 515.738440 | 4.060933 |
| 19 | 70 | 144.005836 | 2.057226 |
| 20 | 24 | 48.444581 | 2.018524 |
| | | | |

Number of Survey Population File Records = 10600

Number of Survey Activity File Records = 52923

Number of Node File Records = 2573

Number of Zone File Records = 85 Highest Zone Number = 92

Number of Link File Records = 3607 Number of Directional Links = 6774

Number of Parking File Records = 7734

Number of Activity Location File Records = 8656

Number of Process Link File Records = 15468

Number of Household File Records = 78716



Number of Population File Records = 229370

Number of Vehicle Type File Records = 14

Number of Vehicle File Records = 174389

Warning: 916 Activity Locations have a Zone Number of Zero

Alexandria Activity Generator Wed Apr 14 11:01:23 2010 ActGen page 4

Household Type Summary

Type Households Surveys Households/Survey

| 1 | 3631 | 478 | 7.6 |
|----|-------|-----|-------|
| 2 | 12217 | 725 | 16.9 |
| 3 | 1708 | 91 | 18.8 |
| 4 | 1877 | 440 | 4.3 |
| 5 | 2471 | 413 | 6.0 |
| 6 | 535 | 59 | 9.1 |
| 7 | 7658 | 613 | 12.5 |
| 8 | 2512 | 239 | 10.5 |
| 9 | 7138 | 219 | 32.6 |
| 10 | 12933 | 341 | 37.9 |
| 11 | 4906 | 90 | 54.5 |
| 12 | 1453 | 111 | 13.1 |
| 13 | 1114 | 69 | 16.1 |
| 14 | 2395 | 226 | 10.6 |
| 15 | 2259 | 69 | 32.7 |
| 16 | 2135 | 91 | 23.5 |
| 17 | 1355 | 67 | 20.2 |
| 18 | 4986 | 127 | 39.3 |
| 19 | 3032 | 70 | 43.3 |
| 20 | 2401 | 24 | 100.0 |
| | | | |

Number of Households = 78716 Number of Persons = 229370 Number of Workers = 134074

Persons per Household = 2.91 Workers per Household = 1.70

Number of Households with Match Problems = 16164 (20.5%) Number of Persons with Match Problems = 22884 (10.0%)

Number of Persons matched to a different Age Group = 30214 (14.6%) Number of Persons matched to a different Work Status = 54874 (26.6%) Number of Persons matched to a different Gender = 59509 (28.8%)

Number of Activities Generated = 1148202 Number of Activities with Problems = 50405 (4.4%) Number of Activities Written = 1133718 (98.7%)

Activities per Household = 18.12



Activities per Person = 5.49

Alexandria Activity Generator Wed Apr 14 11:01:43 2010 ActGen page 5

Trip Length Summary

| Distance (meters) Time (minutes) | | | | | | | | | | | |
|----------------------------------|---------|-----|--------|-----------------|-------|---------|--------|----------|---------|---------|--------|
| Purpos | e Trips | Min | imum N | I aximum | Avera | ige Sto | dDev N | Minimum | Maximum | Average | StdDev |
| • | • | | | | | | | | | | |
| 1 | 69389 | 0 | 10261 | 1482 | 1181 | 0.00 | 131.3 | 5 2.60 | 4.58 | | |
| 2 | 28996 | 0 | 10579 | 1471 | 1180 | 0.00 | 118.5 | 8 3.03 | 4.85 | | |
| 3 | 22552 | 0 | 10196 | 1586 | 1184 | 0.00 | 80.58 | 3.02 | 4.36 | | |
| 4 | 29439 | 0 | 9637 | 1303 | 1165 | 0.00 | 133.08 | 8 4.38 | 8.00 | | |
| 5 | 60105 | 0 | 9362 | 873 | 1162 | 0.00 | 141.00 | 3.05 | 6.93 | | |
| 6 | 36122 | 0 | 9706 | 1579 | 1200 | 0.00 | 90.87 | 2.08 | 3.08 | | |
| 7 | 16665 | 0 | 7928 | 749 | 752 | 0.00 | 125.00 | 4.23 | 7.25 | | |
| 8 | 19463 | 0 | 10216 | 1443 | 1140 | 0.00 | 87.25 | 5 2.23 | 3.40 | | |
| 9 | 57190 | 0 | 10429 | 1341 | 1124 | 0.00 | 124.9 | 0 2.16 | 4.09 | | |
| 11 | 10007 | 0 | 10023 | 1582 | 1198 | 0.00 | 64.9 | 0 2.96 | 4.14 | | |
| 12 | 41815 | 0 | 9380 | 1507 | 1110 | 0.00 | 72.00 | 2.95 | 4.25 | | |
| 13 | 22142 | 0 | 8856 | 1468 | 1093 | 0.00 | 95.85 | 5 3.50 | 5.23 | | |
| 14 | 45366 | 0 | 9940 | 1312 | 1049 | 0.00 | 97.87 | 7 3.54 | 5.54 | | |
| 15 | 30565 | 0 | 9761 | 1217 | 1086 | 0.00 | 93.78 | 3 2.87 | 4.95 | | |
| 16 | 35364 | 0 | 9083 | 1560 | 1159 | 0.00 | 86.65 | 5 2.14 | 2.89 | | |
| 17 | 5789 | 0 | 8698 | 1614 | 1210 | 0.00 | 60.83 | 2.76 | 4.04 | | |
| 18 | 27009 | 0 | 9188 | 1238 | 1134 | 0.00 | 72.62 | 2.04 | 3.10 | | |
| 19 | 1855 | 0 | 7858 | 1616 | 1213 | 0.00 | 27.97 | 2.45 | 3.07 | | |
| | | | | | | | | | | | |
| Total | 559833 | (| 1057 | 9 1349 | 9 115 | 8 0.0 | 00 141 | 1.00 2.8 | 4 5.06 | | |

Tour Length Summary

----- Distance (meters) ----- Time (minutes) -----Trips Minimum Maximum Average StdDev Minimum Maximum Average StdDev Purpose 0.00 397.10 7.54 13.01 0.00 76.65 8.60 8.14 0.40 63.35 6.66 7.01 0.17 188.43 10.01 12.78 0.00 143.45 13.47 13.17 0.17 130.32 4.64 6.52 0.00 188.95 7.51 11.78 0.00 178.25 5.55 8.80 0.03 203.15 5.06 9.67 1.22 214.00 16.56 23.36 0.03 104.78 5.57 6.03 0.00 147.48 6.63 8.93 0.00 172.88 7.12 9.15 0.00 188.17 6.70 11.82 95.47 3.32 4.47 0.00 0.80 164.63 15.70 19.42 0.07 154.85 5.39 8.53 0.45 70.60 10.42 9.54 0.00 397.10 Total 6.44 10.19



Trip Purpose Summary

| | | - Dista | ance (m | eters) | | T | ime (mi | nutes) - | | | |
|------------|-------------|----------|--------------|--------------|--------------|-------------|----------------|--------------|--------------|---------|--------|
| Purpose | Trips | Mini | mum M | aximum | Avera | ge Std | Dev Mi | inimum | Maximum | Average | StdDev |
| 0.1 | 27021 | 0 | 0016 | 1560 | 1045 | 0.00 | 26.20 | 2.20 | 2.05 | | |
| 0-1 | 37821 | 0 | 8916 | 1560 | 1045 | 0.00 | 36.20 58.58 | 2.29 | 2.85 | | |
| 0-2 | 7066 | 0 | 8515 | 1348 | 980 | 0.00 | | 3.96 | 5.54 | | |
| 0-3 | 6630 | 0 | 8546 | 1599 | 1108 | 0.00 | 34.65 | 2.56 | 3.32 | | |
| 0-4 | 8770 | 0 | 7535 | 1318 | 957 | | 104.20 | 3.96 | 5.96 | | |
| 0-5 | 7906 | 0 | 8134 | 1393 | 1022 | 0.00 | 94.82 | 4.66 | 6.18 | | |
| 0-6 | 17343 | 0 | 8744 | 1405 | 1071 | 0.00 | 90.87 | 1.82 | 2.60 | | |
| 0-7 | 11166 | 31 | 6852 | 918 | 645 | | 107.92 | 4.98 | 6.79 | | |
| 0-8 | 14759 | 0 | 7358 | 1441 | 1002 | 0.00 | 40.07 | 2.14 | 2.65 | | |
| 0-9 | 39029 | 0 | 10429 | 1515 | 1021 | 0.00 | | | 2.21 | | |
| 0-11 | 826 | 30 | 6590 | 1763 | 1164 | 0.05 | 22.33 | 2.12 | 1.91 | | |
| 0-12 | 24276 | 32 | | | 962 | 0.03 | | | 4.79 | | |
| 0-13 | 14072 | 0 | 8456 | 1397 | 974 | 0.00 | 95.85 | 3.80 | 5.47 | | |
| 0-14 | 31109 | 0 | 9032 | 1289 | 915 | 0.00 | 69.75 | 3.77 | 5.42 | | |
| 0-15 | 17443 | 0 | 8424 | 1308 | 927 | 0.00 | 51.88 | 2.88 | 4.28 | | |
| 0-16 | 22963 | 0 | 8753 | 1435 | 1054 | 0.00 | | | 2.76 | | |
| 0-17 | 631 | 59 | 8681 | 1757 | 1333 | 0.05 | 33.68 | 2.89 | 3.81 | | |
| 0-18 | 17498 | 0 | 8106 | 1365 | 975 | 0.00 | 56.57 | 2.20 | 2.94 | | |
| 0-19 | 185 | 34 | 5188 | 1383 | 992 | 0.03 | 27.25 | 3.46 | 4.86 | | |
| 1-0 | 30267 | 0 | 8867 | 1551 | 1044 | 0.00 | 79.83 | 2.10 | 2.63 | | |
| 1-1 | 1360 | 0 | 10261 | 1457 | 1442 | 0.00 | 27.45 | 1.93 | 2.65 | | |
| 1-2 | 3758 | 0 | 8877 | 1779 | 1296 | | 112.70 | 3.04 | 5.86 | | |
| 1-3 | 6091 | 0 | 10196 | 1682 | 1238 | 0.00 | 80.58 | 3.26 | 4.81 | | |
| 1-4 | 3273 | 0 | 9208 | 1584 | 1308 | 0.00 | 100.35 | 3.43 | 6.51 | | |
| 1-5 | 13118 | 0 | 9355 | 995 | 1237 | 0.00 | 131.35 | 3.63 | 8.31 | | |
| 1-6 | 4937 | 0 | 9688 | 1836 | 1289 | 0.00 | 10.75 | 2.03 | 1.43 | | |
| 1-8 | 686 | 0 | 9230 | 1739 | 1392 | 0.00 | 10.25 | 1.95 | 1.54 | | |
| 1-11 | 4907 | 0 | 10023 | 1578 | 1184 | 0.00 | | | 3.44 | | |
| 2-0 | 17018 | 0 | 8977 | 1422 | 1084 | 0.00 | 59.95 | 2.85 | 4.16 | | |
| 2-1 | 1212 | 0 | 9339 | 1569 | 1256 | 0.00 | 100.10 | 5.22 | 8.22 | | |
| 2-2 | 3164 | 0 | 9010 | 1487 | 1264 | 0.00 | 43.68 | 2.77 | 4.06 | | |
| 2-3 | 1456 | 0 | 8590 | 1521 | 1183 | 0.00 | 25.45 | 2.53 | 3.30 | | |
| 2-4 | 1659 | 0 | 9536 | 1581 | 1195 | 0.00 0.00 | 29.37 | 2.03 | 2.05 | | |
| 2-5 2-6 | 1539 974 | $0 \\ 0$ | 7515 7044 | 1471 1782 | 1150 1221 | | 64.27 7.82 | 4.22 1.97 | 6.02 1.36 | | |
| 2-8 | 208 | 0 | 7356 | 1380 | 1215 | 0.00 0.00 | 32.80 | 6.43 | 6.94 | | |
| 2-8 2-9 | 919 | 0 | 8558 | | 1213 | 0.00 | 25.27 | 2.58 | 3.06 | | |
| 2-11 | 106 | 173 | 5753 | 1713 | 1156 | | | 1.90 | 1.28 | | |
| 2-11 | 178 | 91 | 7355 | 1660 | 1150 | 0.10 | | 1.84 | 1.28 | | |
| 2-17 | 297 | 0 | 7764 | 1376 | 1213 | 0.10 | | 5.40 | 6.05 | | |
| 2-18 | 88 | 97 | 4952 | 1460 | 969 | 0.10 | 13.20 | 1.92 | 1.86 | | |
| 3-0 | 8944 | 0 | 11586 | 1611 | 1138 | 0.00 | 59.83 | 3.30 | 4.74 | | |
| 3-0 | 2708 | 0 | 9574 | 1797 | 1274 | | 111.43 | 2.84 | 5.10 | | |
| 3-1 | 1895 | 0 | 9449 | 1429 | 1241 | 0.00 | 73.12 | 3.36 | 4.81 | | |
| 3-2 | 2214 | 0 | 8426 | 1599 | 1194 | 0.00 | 32.25 | 2.59 | 3.40 | | |
| 3-3 | 756 | 0 | 6899 | 1527 | 1206 | 0.00 | 19.17 | 2.14 | 2.30 | | |
| 3-4 | 2154 | 0 | 8460 | 1377 | 1223 | | 141.00 | 4.97 | 8.15 | | |
| 3-6 | 794 | 40 | 9198 | 1852 | 1311 | | 15.08 | 2.09 | 1.54 | | |
| 3-7 | 85 | 46 | 6031 | 1203 | 1156 | | 57.63 | | 11.97 | | |
| <i>-</i> , | 00 | | 5551 | | | J. 2 / | 2 | 0.07 | | | |



| 3-8 | 546 | 0 | 8698 | 1997 | 1604 | 0.00 | 9.65 | 2.23 | 1.77 |
|------|-------|------|------|------|------|------|--------|------|------|
| 3-9 | 1023 | 0 | 8630 | 1597 | 1217 | 0.00 | 28.05 | 2.65 | 3.62 |
| 3-11 | 850 | 0 | 7886 | 1848 | 1291 | 0.00 | 16.75 | 2.16 | 1.74 |
| 3-17 | 315 | 100 | 5726 | 1571 | 1066 | 0.13 | 25.53 | 2.33 | 3.25 |
| 3-18 | 247 | 0 | 8640 | 1521 | 1244 | 0.00 | 29.18 | 2.18 | 2.93 |
| 3-19 | 12 | 1076 | 3891 | 2223 | 944 | 1.18 | 4.32 | 2.46 | 1.05 |
| 4-0 | 12899 | 0 | 7883 | 1437 | 1066 | 0.00 | 104.88 | 3.92 | 5.65 |
| 4-1 | 2160 | 0 | 9389 | 1488 | 1320 | 0.00 | 47.82 | 4.20 | 5.29 |
| 4-2 | 1461 | 0 | 8949 | 1606 | 1188 | 0.00 | 31.80 | 2.47 | 3.25 |

Trip Purpose Summary

----- Distance (meters) ------ Time (minutes) ------Purpose Trips Minimum Maximum Average StdDev Minimum Maximum Average StdDev 4-3 224 0 7535 1484 1321 0.00 47.22 2.33 5.20 4-4 4139 0 8187 1057 1016 0.00 99.77 7.56 10.28 4-5 2413 0 7853 1133 1218 0.0069.93 2.39 4.76 0 2.23 4-6 768 6113 1461 1087 0.00 65.88 4.71 474 987 4-7 0 6285 832 0.00 52.38 4.08 7.65 780 1649 87.25 4-8 0 10216 1895 0.00 3.52 7.29 4-9 814 0 7635 1231 1353 0.00 55.63 3.43 6.61 4-11 113 150 4814 1604 956 0.17 45.15 3.32 5.95 6753 1927 7.50 4-17 64 135 1331 0.15 2.13 1.48 4-18 688 0 8932 1466 1381 0.00 9.92 1.63 1.53 5-0 13452 8485 1521 1068 0.00 61.45 2.44 3.34 0 5-1 13497 9215 1002 1266 0.00 131.35 3.36 7.72 0 5-2 1753 0 8545 1522 1160 0.00 67.68 2.70 4.59 0 7550 61.90 6.97 5-3 1423 1126 1008 0.006.77 5-4 3092 0 8694 881 1187 0.00 74.05 2.16 4.96 5-5 2829 0 7150 1026 947 0.00 86.37 6.92 9.01 5-6 861 0 8694 1726 1380 0.00 79.73 3.64 6.59 5-7 0.00 125.00 3870 0 7500 171 594 1.68 7.05 5-8 1161 0 8009 662 1272 0.00 86.92 2.00 6.58 5-9 9362 530 992 7.22 10198 0 0.00 101.07 2.35 5-11 691 0 8789 1567 1265 0.00 32.38 3.40 4.76 5-17 843 0 8227 1557 1171 0.00 54.55 3.93 6.16 8558 5-18 5610 661 1243 0.00 72.62 1.37 3.57 0 7.31 5-19 41 0 3162 731 540 0.00 23.57 9.30 6-0 15146 0 8138 1448 1092 0.00 51.67 1.89 2.42 0 1805 1271 0.00 12.52 2.00 6-1 5914 9688 1.42 6-2 1496 0 7351 1644 1296 0.00 8.17 1.82 1.44 6-3 0 7611 1653 1250 0.00 22.77 2.02 2.10 1113 6-4 954 0 8802 1812 1339 0.00 77.88 2.67 4.08 6-5 944 0 8192 1650 1250 0.00 54.57 2.96 5.06 4615 0 9099 1641 1310 0.00 60.40 2.55 4.70 6-6 7928 15.85 6-7 507 0 1307 1119 0.00 2.05 1.84 796 8450 1882 1298 0.00 9.38 2.16 6-8 0 1.49 7936 6-9 2772 0 1781 1284 0.00 59.13 2.01 1.91 6-11 72 0 6163 2074 1450 0.00 6.83 2.30 1.61 1748 6-12 42 0 4096 1109 0.00 4.55 1.93 1.23 2 1007 5223 3115 2981 5.80 6-13 1.12 3.46 3.31 10 2.92 6-14 1592 5112 2633 1151 1.77 5.67 1.28



| 6-15 | 9 | 112 | 3417 | 1097 | 1061 | 0.12 | 3.78 | 1.21 | 1.18 |
|------|-------|-----|-------|------|------|------|--------|------|-------|
| 6-17 | 53 | 114 | 4962 | 1339 | 959 | 0.12 | 5.50 | 1.48 | 1.07 |
| 6-18 | 1632 | 0 | 7300 | 1678 | 1295 | 0.00 | 22.25 | 2.16 | 2.16 |
| 6-19 | 21 | 255 | 5395 | 2009 | 1361 | 0.28 | 5.98 | 2.22 | 1.51 |
| 7-0 | 10704 | 0 | 6508 | 887 | 598 | 0.00 | 107.92 | 5.19 | 7.16 |
| 7-2 | 162 | 0 | 5761 | 1523 | 1155 | 0.00 | 82.28 | 8.80 | 13.71 |
| 7-3 | 209 | 0 | 7470 | 1381 | 1438 | 0.00 | 57.63 | 4.98 | 10.37 |
| 7-4 | 2461 | 0 | 8657 | 1108 | 1217 | 0.00 | 114.32 | 6.94 | 12.84 |
| 7-5 | 4023 | 0 | 6825 | 201 | 653 | 0.00 | 113.75 | 2.45 | 9.12 |
| 7-6 | 202 | 96 | 8740 | 1742 | 1346 | 0.18 | 12.35 | 2.39 | 1.92 |
| 7-7 | 563 | 0 | 6018 | 735 | 874 | 0.00 | 100.30 | 8.55 | 12.09 |
| 8-0 | 8337 | 0 | 7991 | 1357 | 990 | 0.00 | 104.20 | 2.48 | 3.82 |
| 8-1 | 840 | 0 | 7628 | 1653 | 1284 | 0.00 | 17.12 | 1.90 | 1.68 |
| 8-2 | 1101 | 0 | 10579 | 1904 | 1491 | 0.00 | 38.93 | 3.29 | 4.04 |
| 8-3 | 378 | 0 | 6502 | 1688 | 1291 | 0.00 | 8.40 | 1.95 | 1.45 |
| 8-4 | 668 | 0 | 7985 | 1643 | 1310 | 0.00 | 133.08 | 6.12 | 12.34 |
| 8-5 | 6419 | 0 | 8541 | 296 | 849 | 0.00 | 90.98 | 0.89 | 4.55 |
| 8-6 | 568 | 0 | 7109 | 1666 | 1221 | 0.00 | 27.75 | 2.74 | 3.41 |
| 8-8 | 326 | 0 | 5950 | 597 | 1041 | 0.00 | 19.97 | 1.12 | 2.28 |

Trip Purpose Summary

| D | | | | | | | ime (mi | | | A | C4JD |
|---------|-------|------|--------|---------|---------|--------|---------|--------|---------|----------|--------|
| Purpose | rnps | Mini | mum IV | ıaxımum | i Avera | ge Sic | ibev Mi | ınımum | Maximum | Average | Stabev |
| 8-9 | 662 | 0 | 7494 | 1037 | 975 | 0.00 | 124.90 | 5.68 | 13.57 | | |
| 8-11 | 10 | 690 | 2056 | 1111 | 420 | 0.77 | 2.28 | 1.23 | 0.47 | | |
| 8-18 | 305 | 0 | 9188 | 2066 | 1640 | 0.00 | 10.20 | 2.29 | 1.82 | | |
| 9-0 | 32794 | 0 | 10429 | 1495 | 1020 | 0.00 | 89.70 | 2.14 | 3.03 | | |
| 9-2 | 2940 | 0 | 8854 | 1762 | 1257 | 0.00 | 57.28 | 2.72 | 3.71 | | |
| 9-3 | 1594 | 0 | 8249 | 1567 | 1166 | 0.00 | 57.35 | 2.46 | 3.52 | | |
| 9-4 | 2175 | 0 | 9637 | 1529 | 1343 | 0.00 | 103.80 | 4.90 | 10.25 | | |
| 9-5 | 11529 | 0 | 9362 | 634 | 1078 | 0.00 | 101.07 | 2.07 | 6.12 | | |
| 9-6 | 2882 | 0 | 9706 | 1747 | 1259 | 0.00 | 55.72 | 2.37 | 3.58 | | |
| 9-8 | 135 | 80 | 8095 | 1646 | 1221 | 0.08 | 8.98 | 1.82 | 1.36 | | |
| 9-9 | 497 | 0 | 4562 | 360 | 777 (| 0.00 | 54.50 | 1.58 | 5.15 | | |
| 9-17 | 2231 | 0 | 7643 | 1651 | 1218 | 0.00 | 60.83 | 2.79 | 3.96 | | |
| 11-0 | 1869 | 0 | 9633 | 1766 | 1223 | 0.00 | 116.05 | 4.09 | 6.95 | | |
| 11-1 | 3877 | 0 | 10023 | 1617 | 1212 | 0.00 | 92.13 | 2.48 | 4.46 | | |
| 11-2 | 57 | 40 | 6093 | 1593 | 1132 | 0.03 | 6.77 | 1.76 | 1.26 | | |
| 11-3 | 593 | 76 | 7736 | 1785 | 1218 | 0.08 | 8.58 | 1.98 | 1.35 | | |
| 11-4 | 206 | 0 | 7028 | 1386 | 1125 | 0.00 | 24.75 | 4.22 | 5.01 | | |
| 11-5 | 696 | 0 | 9321 | 1486 | 1137 | 0.00 | 45.40 | 3.30 | 4.99 | | |
| 11-6 | 311 | 0 | 7453 | 1995 | 1335 | 0.00 | 24.97 | 2.46 | 2.37 | | |
| 11-11 | 2432 | 0 | 9994 | 1422 | 1162 | 0.00 | 64.90 | 4.46 | 5.72 | | |
| 12-0 | 29297 | 0 | 8807 | 1445 | 1002 | 0.00 | | 3.13 | 4.70 | | |
| 12-6 | 49 | 0 | 6059 | 1905 | 1395 | 0.00 | 6.72 | 2.11 | 1.55 | | |
| 12-12 | 5465 | 0 | 8225 | 1574 | 1257 | 0.00 | 34.02 | 2.14 | 2.54 | | |
| 12-13 | 1372 | 0 | 8246 | 1563 | 1225 | 0.00 | 26.35 | 2.47 | 3.06 | | |
| 12-14 | 2447 | 0 | 9848 | 1602 | 1245 | 0.00 | 87.37 | 3.08 | 6.12 | | |
| 12-15 | 1716 | 0 | 8652 | 1359 | 1218 | 0.00 | 33.98 | 2.04 | 2.83 | | |
| 12-16 | 1470 | 0 | 7945 | 1797 | 1255 | 0.00 | | 1.99 | 1.39 | | |
| 13-0 | 10778 | 0 | 9165 | 1373 | 963 | 0.00 | 95.85 | 4.03 | 5.75 | | |



```
1007
13-6
          2
                      5223
                              3115
                                     2981
                                             1.12
                                                    5.80
                                                           3.46
                                                                  3.31
13-12
         3974
                  0
                       9380
                              1762
                                      1337
                                             0.00
                                                    38.35
                                                            2.98
                                                                   3.67
13-13
         2189
                  0
                       8856
                              1561
                                      1255
                                             0.00
                                                    77.53
                                                            4.28
                                                                   6.95
13-14
         1346
                  0
                       8232
                              1263
                                      1183
                                             0.00
                                                    50.78
                                                            3.73
                                                                   5.49
                                                    93.78
                                                            3.26
                                                                   5.59
13-15
         1862
                  0
                       8399
                              1577
                                      1256
                                             0.00
13-16
         2085
                  0
                       8884
                              1898
                                      1356
                                             0.00
                                                    39.27
                                                            2.17
                                                                   2.01
14-0
                                      935
        30382
                  0
                       8694
                              1318
                                             0.00
                                                   81.28
                                                            3.98
                                                                   5.74
                                                    5.60
14-6
          10
                415
                      5050
                              1370
                                      1376
                                             0.45
                                                           1.51
                                                                  1.53
14-12
         2500
                  0
                       8402
                              1585
                                      1190
                                             0.00
                                                    72.00
                                                            2.82
                                                                   4.93
         1499
                  0
                       7895
                                      1250
                                                    31.17
                                                            2.64
                                                                   3.91
14-13
                              1382
                                             0.00
14-14
         4352
                  0
                       8364
                              1155
                                      1168
                                             0.00
                                                    97.87
                                                            3.63
                                                                   7.10
                                                   66.53
14-15
         5618
                  0
                       8561
                               604
                                      1081
                                             0.00
                                                            1.74
                                                                   5.30
14-16
                                      1327
                                                    55.07
                                                                   2.48
         2615
                  0
                       9083
                              1761
                                             0.00
                                                            2.16
15-0
        17697
                  0
                       8424
                              1345
                                      966
                                             0.00
                                                   90.22
                                                            2.93
                                                                   4.40
15-6
                      5998
                              2440
                                      1905
                                                    6.65
                                                           2.70
                                                                  2.11
          17
                606
                                             0.67
15-12
         2597
                  0
                       8255
                              1640
                                      1277
                                             0.00
                                                    32.12
                                                            2.14
                                                                   2.40
15-13
         1416
                  0
                       8263
                              1514
                                      1233
                                             0.00
                                                    50.58
                                                            2.79
                                                                   4.55
15-14
         3591
                  0
                       9940
                              1101
                                      1247
                                             0.00
                                                    84.17
                                                            2.53
                                                                   5.23
15-15
         1822
                  0
                       7748
                              1045
                                      1000
                                             0.00
                                                    81.67
                                                            6.39
                                                                   8.48
15-16
         1742
                  0
                       7744
                              1824
                                      1257
                                             0.00
                                                    86.65
                                                            2.71
                                                                   5.37
16-0
        21631
                  0
                       9245
                              1484
                                      1071
                                             0.00
                                                   109.55
                                                             2.01
                                                                   2.74
                                                    4.90
16-6
          16
                400
                      4416
                              2203
                                      1406
                                             0.43
                                                           2.44
                                                                  1.56
                                                            2.49
16-12
         2961
                  0
                       8403
                              1757
                                      1263
                                             0.00
                                                    33.38
                                                                   2.99
                                                    21.87
                                                            2.20
16-13
         1592
                  0
                       7464
                              1923
                                      1289
                                                                   1.67
                                              0.00
16-14
         2511
                  0
                       9865
                              1900
                                      1451
                                              0.00
                                                    46.30
                                                            2.37
                                                                   2.77
16-15
         2095
                  0
                       9761
                              1818
                                      1353
                                             0.00
                                                    36.93
                                                            3.16
                                                                   4.26
                  0
                       8994
16-16
         4489
                              1745
                                      1292
                                             0.00
                                                    65.72
                                                            2.35
                                                                   3.03
17-0
         1964
                      7742
                              1917
                                      1231
                                             0.00
                                                   60.25
                                                            2.40
                                                                   2.74
                  0
17-2
         174
                     5321
                                     876
                 0
                             1113
                                            0.00 44.00
                                                          7.04
                                                                 7.39
```

Trip Purpose Summary

| StdDev |
|--------|
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |
| |



```
19-4
         44
              170
                   4902
                           1681
                                 1077 0.18
                                             5.43
                                                    1.86
                                                          1.20
19-5
                   8293
                          1654
                                                          1.27
         436
                                 1143
                                       0.00
                                              9.20
                                                    1.83
               0
19-6
         20
              111
                    5028
                           1960
                                 1392
                                        0.12
                                              5.58
                                                    2.17
                                                          1.55
19-18
         400
                           1405
                                                           3.66
                0
                    5661
                                 1134
                                        0.00
                                             25.02
                                                    2.87
19-19
         337
                    6355
                           1590
                                 1271
                                        0.00
                                             27.97
                                                     3.03
                                                           3.92
Total
       836291
                 0
                    11586
                            1377 1117 0.00 141.00 2.87 4.89
```

Tour Purpose Summary

| Purpose | | I | Distance | (meters) | | | Time (n | ninutes) | | | |
|---------|-------|-------|----------|----------|-------|-------|---------|----------|-------|---------|--------|
| -Stops | | | | | | | | | | Average | StdDev |
| • | - | | | | | | | | | | |
| 1-1 | 16866 | 0 | 11780 | 1859 | 1352 | 0.00 | 61.60 | 2.88 | 3.64 | | |
| 1-2 | 8828 | 66 | 19638 | 3729 | 2309 | 0.23 | 61.80 | 4.99 | 4.15 | | |
| 1-3 | 10075 | 0 | 24221 | 4097 | 2878 | 0.00 | 267.48 | 7.85 | 13.38 | | |
| 1-4 | 5994 | 150 | 26209 | 6221 | 3506 | 0.32 | 230.87 | 10.71 | 12.90 | | |
| 1-5 | 3229 | 651 | 34725 | 6750 | 4058 | 0.72 | 208.20 | 16.13 | 19.63 | | |
| 1-6 | 1483 | 970 | 42068 | 9364 | 5013 | 1.17 | 397.10 | 22.24 | 29.78 | | |
| 1-7 | 928 | 2501 | 39745 | 11144 | 5733 | 3.40 | 144.65 | 26.06 | 27.22 | | |
| 1-8 | 601 | 3094 | 31160 | 12918 | 5178 | 3.38 | 109.27 | 18.37 | 14.15 | | |
| 1-9 | 130 | 4131 | 28775 | 12983 | 4491 | 7.07 | 126.18 | 31.48 | 22.27 | | |
| 1-10 | 55 | 8220 | 33029 | 17740 | 5966 | 9.03 | 36.63 | 19.63 | 6.63 | | |
| 1-12 | 80 | 8750 | 51357 | 24274 | 10630 | 9.63 | 57.00 | 26.88 | 11.81 | | |
| 1-14 | 36 | 13131 | 30677 | 20496 | 4716 | 14.5 | 2 33.97 | 22.6 | | | |
| 2-1 | 4425 | 63 | 12125 | 2501 | 1466 | 0.23 | 60.47 | 7.75 | 8.68 | | |
| 2-2 | 1290 | 0 | 15980 | 4566 | 2514 | 0.00 | 37.78 | 5.32 | 3.29 | | |
| 2-3 | 552 | 1054 | 15386 | 5212 | 2700 | 1.70 | 64.60 | 13.61 | 10.20 | | |
| 2-4 | 223 | 2337 | 20688 | 7748 | 3432 | 3.27 | 76.65 | 16.20 | 12.97 | | |
| 2-5 | 117 | 3781 | 24825 | 10764 | 4459 | 4.17 | 27.53 | 11.92 | 4.95 | | |
| 2-6 | 2 | 4558 | 6068 | 5313 | 1068 | 7.45 | 8.88 | 3.17 1 | .01 | | |
| 2-11 | 10 | 9095 | 22813 | 14599 | 4936 | 9.98 | 25.27 | 16.11 | 5.50 | | |
| 3-1 | 1968 | 146 | 10238 | 2869 | 1499 | 0.40 | 63.35 | 6.11 | 7.37 | | |
| 3-2 | 677 | 556 | 15176 | 4311 | 2433 | 0.60 | 51.50 | 7.90 | 8.60 | | |
| 3-3 | 714 | 537 | 22645 | 5913 | 2977 | 0.58 | 25.13 | 6.54 | 3.31 | | |
| 3-4 | 69 | 2402 | 15031 | 8042 | 3112 | 2.65 | 16.67 | 8.90 | 3.46 | | |
| 3-5 | 9 | 3701 | 12569 | 7952 | 3093 | 4.07 | 13.92 | 8.79 | 3.43 | | |
| 3-7 | 15 | 7192 | 22265 | 14785 | 4554 | 7.93 | 24.67 | 16.37 | 5.05 | | |
| 4-1 | 4878 | 43 | 11502 | 2655 | 1529 | 0.17 | 102.23 | 6.76 | 8.24 | | |
| 4-2 | 1339 | 145 | 18756 | 3207 | 2199 | 0.55 | 98.12 | 15.40 | 15.80 | | |
| 4-3 | 505 | 438 | 18238 | 5420 | 3065 | 0.47 | 188.43 | 15.37 | 16.89 | | |
| 4-4 | 282 | 320 | 18418 | 5978 | 3780 | 1.58 | 105.15 | 20.95 | 19.43 | | |
| 4-5 | 144 | 460 | 21392 | 4645 | 3925 | 4.30 | 99.25 | 23.55 | 21.33 | | |
| 4-6 | 68 | 1863 | 21284 | 9997 | 4236 | 4.78 | 93.60 | 19.22 | 18.82 | | |
| 4-7 | 12 | 1027 | 2741 | 1663 | 499 1 | 7.12 | 45.68 | 27.71 | 8.32 | | |
| 4-8 | 1 | 7281 | 7281 | 7281 | 0 23 | .32 2 | 3.32 23 | 3.32 0 | .00 | | |
| 5-1 | 1953 | 214 | 12822 | 2580 | 1483 | 0.23 | 52.97 | 7.06 | 7.46 | | |
| 5-2 | 1632 | 0 | 16192 | 3517 | 1847 | 0.00 | 80.03 | 19.24 | 12.75 | | |
| 5-3 | 360 | 712 | 18538 | 4995 | 2813 | 0.75 | 73.72 | 17.56 | 16.08 | | |
| 5-4 | 202 | 626 | 17948 | 5321 | 3651 | 1.03 | 143.45 | 21.31 | 23.63 | | |
| 5-5 | 27 | 4742 | 21864 | 11530 | 4071 | 5.22 | 24.25 | 12.77 | 4.53 | | |
| 5-6 | 73 | 2564 | 27190 | 12238 | 5936 | 3.40 | 42.80 | 14.59 | 7.77 | | |
| 5-8 | 1 | 3854 | 3854 | 3854 | 0 4. | 90 4 | .90 4.9 | 0.0 | 00 | | |



```
6-1
       4120
               155
                    12344
                            2876
                                   1685
                                          0.17
                                                48.70
                                                        3.75
                                                               3.69
6-2
                                                         7.83
       1051
               790
                    15743
                            5204
                                   2616
                                          0.85
                                                130.32
                                                              12.03
6-3
       132
              1623
                    24116
                            6336
                                   3889
                                          1.78
                                                26.77
                                                        7.01
                                                              4.32
7-1
       6996
               34
                    7121
                            934
                                  670
                                        0.05 107.92
                                                      5.33
                                                             7.83
7-2
       1395
               39
                   15592
                            1937
                                          0.05 119.85
                                   1721
                                                      10.55 14.84
7-3
       2314
               0
                   19068
                           1676
                                   1988
                                         0.00 188.95
                                                        8.25
                                                              13.66
7-4
                   15711
                                   1693
                                          0.42 104.77
                                                       12.24
       885
              152
                            2131
                                                              14.51
7-5
        288
              31
                   16445
                           3467
                                  3155
                                         0.27
                                               100.33
                                                       16.25
                                                              15.16
              215
7-6
        205
                   29636
                           2357
                                   3083
                                          0.35
                                              150.88
                                                       13.61
                                                              27.35
7-7
        38
                   12786
                           2406
                                  2248
                                         6.00
                                               66.78 27.06
             380
                                                             13.04
7-8
        84
             4490
                   23942
                           12759
                                   4574
                                          5.53
                                                26.55
                                                       14.18
                                                               5.01
7-9
            8483
                   16306
                           11826
                                   3608
                                                       13.09
        6
                                          9.37
                                               18.07
                                                               4.01
8-1
               58
                   14560
                            1825
                                   1471
                                          0.05 111.13
                                                        3.13
                                                               4.67
       6438
8-2
       5770
               70
                   14348
                            3190
                                   1663
                                          0.07
                                                62.83
                                                        3.84
                                                              2.89
                                                        9.35
8-3
       1336
               73
                   16312
                            3544
                                   2746
                                          0.12 178.25
                                                             14.85
8-4
                  15938
                                  3502
                                               98.07 12.94
       652
               0
                           5645
                                         0.00
                                                            14.16
8-5
        891
              483
                   35485
                            9036
                                   5186
                                          0.80 42.50 11.02
                                                               5.78
```

Tour Purpose Summary

| Purpose | | | | | | | | | | | | |
|---------|-------|-------|--------|---------|--------|-------|---------|--------|--------|---------|--------|--|
| -Stops | Trips | Minim | um Max | kimum A | verage | StdDe | v Minin | num Ma | aximum | Average | StdDev | |
| | | | | | | | | | | | | |
| 8-6 | 633 | 1812 | 28647 | 8701 | 4135 | | 131.37 | 13.15 | 15.43 | | | |
| 8-7 | 89 | 1232 | 20796 | 5625 | 3718 | | 150.47 | 43.45 | 35.40 | | | |
| 8-10 | 214 | 7072 | 34331 | 15672 | 5080 | | | 17.34 | 5.64 | | | |
| 9-1 | 22528 | | 13351 | 1783 | 1306 | 0.03 | 57.05 | 2.56 | 3.47 | | | |
| 9-2 | 5396 | 59 | 17254 | 3295 | 2143 | | 124.90 | 4.93 | 6.31 | | | |
| 9-3 | 10110 | | 22970 | 3220 | 2595 | 0.05 | 203.15 | 5.96 | 9.90 | | | |
| 9-4 | 2710 | 168 | 29055 | 5267 | 3226 | | 193.40 | 9.38 | 13.98 | | | |
| 9-5 | 2003 | 183 | 23435 | 6624 | 4057 | 0.30 | 183.63 | 15.11 | 22.64 | | | |
| 9-6 | 587 | 1314 | 27426 | 7894 | 4249 | 1.43 | 110.22 | 18.73 | 19.50 | | | |
| 9-7 | 336 | 2353 | 27063 | 10433 | 4403 | 2.57 | 98.17 | 24.84 | 21.27 | | | |
| 9-8 | 20 | 6014 | 24392 | 12273 | 5638 | 6.62 | 85.85 | 20.10 | 17.57 | | | |
| 9-9 | 55 | 6803 | 26610 | 13745 | 4261 | 7.50 | 61.97 | 23.43 | 14.39 | | | |
| 9-11 | 7 | 11051 | 23583 | 16238 | 4667 | 12.20 | 26.13 | 17.96 | 5.19 | | | |
| 11-2 | 44 | 1110 | 13661 | 4971 | 2476 | 1.22 | 15.15 | 5.50 | 2.75 | | | |
| 11-3 | 111 | 1170 | 24091 | 6451 | 3952 | 1.28 | 26.73 | 7.14 | 4.39 | | | |
| 11-4 | 518 | 861 | 22126 | 7156 | 3570 | 1.43 | 66.18 | 9.33 | 7.89 | | | |
| 11-5 | 118 | 1609 | 38609 | 9363 | 4692 | 2.95 | 93.80 | 15.03 | 16.19 | | | |
| 11-6 | 40 | 2089 | 6522 | 4467 | 1138 | 34.82 | 108.70 | 74.45 | 18.97 | | | |
| 11-7 | 63 | 3924 | 20828 | 10635 | 4351 | 4.32 | 101.20 | 14.04 | 13.18 | | | |
| 11-8 | 194 | 2670 | 33139 | 12029 | 5315 | 5.37 | 214.00 | 33.76 | 38.66 | | | |
| 11-9 | 33 | 4762 | 23855 | 13542 | 4822 | 5.23 | 26.43 | 14.97 | 5.36 | | | |
| 11-10 | 6 | 10856 | 26996 | 16898 | 5913 | 11.97 | 7 29.93 | 18.70 | 6.58 | | | |
| 12-1 | 19359 | 33 | 13131 | 2195 | 1497 | 0.03 | 64.97 | 4.92 | 5.88 | | | |
| 12-2 | 4220 | 203 | 20348 | 4046 | 2423 | 0.30 | 51.58 | 5.51 | 4.76 | | | |
| 12-3 | 2413 | 694 | 18984 | 5568 | 2947 | 0.87 | 71.03 | 7.40 | 6.22 | | | |
| 12-4 | 953 | 1255 | 23178 | 7451 | 3870 | 1.58 | 70.68 | 9.86 | 7.11 | | | |
| 12-5 | 488 | 1726 | 23730 | 8530 | 3692 | 1.88 | 26.32 | 9.51 | 4.03 | | | |
| 12-6 | 247 | 3673 | 22786 | 11081 | 3970 | 4.02 | | 12.39 | 4.45 | | | |
| 12-7 | 68 | 5528 | 22331 | 11466 | 3644 | 6.10 | 24.73 | 12.68 | 4.05 | | | |
| 12-8 | 7 | 8386 | 26923 | 13016 | 6645 | 9.25 | 29.87 | 14.41 | 7.38 | | | |



```
5283
12-10
          4
                     6287
                             5701
                                    421
                                          88.05 104.78
                                                         95.02
                                                                 7.02
13-1
        7758
                34
                     10312
                             1801
                                    1381
                                            0.05
                                                  95.85
                                                          5.46
                                                                6.62
13-2
        2418
                 0
                    12853
                             3255
                                    2223
                                           0.00
                                                 56.02
                                                         6.17
                                                                6.85
13-3
        989
               434
                     18410
                             5227
                                    2881
                                            0.47
                                                  93.78
                                                          6.96
                                                                6.64
                                    3048
                                                  97.77
13-4
         463
               953
                     16633
                             7077
                                            1.03
                                                         13.68
                                                                14.85
13-5
         193
                     15702
                             7019
                                    3399
                                                 17.42
                                                          7.91
               611
                                            1.02
                                                                3.61
13-6
                   21588
         48
                0
                            8639
                                   4169
                                          0.00 67.72
                                                      12.90
                                                              12.70
13-7
         38
              2622
                     8849
                             5195
                                    1590 43.70 147.48
                                                          86.58
                                                                 26.51
13-9
         228
              6832
                     45878
                             17536
                                     7257
                                             7.52
                                                   50.87
                                                          19.41
                                                                  8.06
13-10
          6
               354
                     1411
                             772
                                   388
                                                2.35
                                                       1.28
                                         0.58
                                                             0.65
          8
13-12
              13827
                     21113
                             17812
                                      2829
                                            15.25 23.38 19.69
                                                                   3.15
14-1
                              2212
        23070
                 31
                     12519
                                     1465
                                            0.03 110.50
                                                           6.46
                                                                 7.81
                                                                5.78
14-2
                    18522
                             4037
                                                 98.02
                                                         5.82
        5835
                 0
                                    2405
                                           0.00
14-3
        3386
                 0
                    21715
                             4210
                                    2927
                                           0.00
                                                 98.00
                                                         7.45
                                                                8.24
14-4
        1053
                    19995
                             6475
                                    3447
                                            0.10 129.18 10.45
                                                                10.59
                64
14-5
        406
                0
                    31767
                            4633
                                   4802
                                           0.00
                                                 98.23 17.78
                                                               17.01
14-6
         509
                0
                   28120
                            6549
                                   4799
                                           0.00 161.92
                                                         25.09
                                                                22.81
14-7
         122
                0
                    23162
                            9069
                                   4885
                                           0.00
                                                172.88
                                                        34.37
                                                                38.18
14-8
         7
              807
                    12485
                            6310
                                   5096
                                           8.90
                                                21.73
                                                        14.20
                                                                4.64
14-9
         54
              1876
                    24181
                            10553
                                     6480
                                            7.10 35.58
                                                         17.18
                                                                 6.08
14-10
          11
                0
                    5179
                            3738
                                   1357
                                          0.00
                                                86.32
                                                       62.30 22.62
          9
              7342
                            15232
14-11
                     24412
                                     5270
                                            8.08
                                                  27.08
                                                         16.85
                                                                 5.86
                     12504
15-1
        12026
                 41
                              2186
                                     1474
                                            0.03
                                                  63.28
                                                          4.85
                                                                 6.23
15-2
                    14329
        3172
                             3398
                                    2080
                                                 77.37
                                                         5.00
                                                                5.43
                 0
                                           0.00
15-3
        1112
                158
                     19056
                              4818
                                     2988
                                            0.25
                                                  72.13
                                                          7.68
                                                                 7.71
15-4
         585
               888
                     21939
                             7552
                                     3669
                                            1.43
                                                  94.45
                                                         10.45
                                                                 9.81
15-5
         93
                    12626
                             6233
                                    2890
                                            3.63 153.30
                                                         25.46
                                                                 23.45
              1297
```

Tour Purpose Summary

| Purpose | | Г | Distance (| meters) | | | Time (n | ninutes) | | | |
|---------|-------|-------|------------|---------|---------|--------|---------|----------|--------|---------|--------|
| -Stops | Trips | Minim | num Max | kimum A | Average | StdDe | v Minir | num Ma | aximum | Average | StdDev |
| | | | | | | | | | | | |
| 15-6 | 805 | 1587 | 35373 | 10756 | 5319 | 3.93 | 150.97 | 25.48 | 25.75 | | |
| 15-7 | 119 | 0 | 15991 | 6917 | 4131 | 0.00 1 | 188.17 | 67.93 | 59.14 | | |
| 15-8 | 3 | 9956 | 27995 | 16099 | 10304 | 10.97 | 31.05 | 17.81 | 11.47 | | |
| 15-9 | 12 | 8571 | 20027 | 15027 | 3887 | 9.43 | 22.17 | 16.62 | 4.32 | | |
| 15-12 | 1 | 596 | 596 | 596 | 0 9.9 | 3 9.9 | 9.9 | 3 0.00 |) | | |
| 16-1 | 14789 | 0 | 12742 | 1891 | 1412 | 0.00 | 53.98 | 2.62 | 3.18 | | |
| 16-2 | 2030 | 165 | 16203 | 3398 | 2187 | 0.18 | 86.03 | 5.77 | 8.14 | | |
| 16-3 | 872 | 592 | 17768 | 6779 | 3075 | 0.65 | 43.75 | 7.91 | 4.40 | | |
| 16-4 | 122 | 3033 | 17028 | 7730 | 3134 | 3.33 | 18.88 | 8.56 | 3.48 | | |
| 16-5 | 8 | 3706 | 13881 | 8351 | 3757 | 5.65 | 95.47 | 21.51 | 30.16 | | |
| 16-6 | 81 | 3290 | 17441 | 9694 | 3814 | 3.62 | 19.33 | 10.72 | 4.24 | | |
| 17-2 | 123 | 801 | 15053 | 5145 | 2618 | 0.88 | 16.70 | 5.70 | 2.91 | | |
| 17-3 | 184 | 738 | 18691 | 4653 | 3031 | 0.80 | 66.10 | 9.70 | 11.29 | | |
| 17-4 | 22 | 2393 | 10519 | 5933 | 2507 | 2.62 | 11.65 | 6.56 | 2.79 | | |
| 17-5 | 169 | 1076 | 20578 | 7994 | 3621 | 1.72 | 164.63 | 13.93 | 19.87 | | |
| 17-6 | 72 | 1751 | 23632 | 6616 | 3694 | 11.63 | 86.48 | 40.44 | 17.47 | | |
| 17-7 | 19 | 5558 | 19053 | 10934 | 3886 | 6.13 | 21.13 | 12.10 | 4.32 | | |
| 17-8 | 166 | 3945 | 29557 | 13396 | 5445 | 5.48 | 158.42 | 22.44 | 24.41 | | |
| 18-1 | 7254 | 68 | 11112 | 1806 | 1334 | 0.07 | 56.57 | 3.44 | 4.97 | | |
| 18-2 | 5326 | 136 | 14765 | 2401 | 1878 | 0.18 | 70.33 | 3.77 | 4.10 | | |



```
18-3
         3910
                      23732
                              2998
                                     2644
                                             0.08
                                                   89.23
                                                           5.67
                 83
                                                                  8.18
18-4
         1042
                 387
                      18961
                               5242
                                      3281
                                             0.45
                                                   129.83
                                                            9.80
                                                                  14.09
18-5
         1160
                 369
                      24644
                               6011
                                      3875
                                             0.60 154.85
                                                           10.87
                                                                  13.38
18-6
         938
               1104
                     22259
                               8803
                                      4102
                                             1.80
                                                   86.45
                                                          11.09
                                                                  7.90
               2014
                                     3994
18-7
          82
                      21751
                              9324
                                             2.20
                                                   24.13
                                                          10.32
                                                                  4.44
18-8
               2571
                      6565
                              4059
                                     1063
                                           23.03
                                                   64.62
                                                          39.65
          36
                                                                  11.52
                                            29.58
18-9
          57
               2918
                      17211
                              7843
                                     3491
                                                  117.40
                                                           69.43
                                                                 22.45
19-2
          25
               2100
                      13623
                              5365
                                     2960
                                             2.32
                                                   16.72
                                                           6.72
                                                                  3.68
19-3
         192
                418
                      14063
                              6222
                                     2752
                                             0.45
                                                   15.60
                                                           6.88
                                                                 3.06
19-4
          54
               1077
                     14834
                              5227
                                     3101
                                             3.45
                                                   52.78
                                                          16.09
                                                                 13.95
19-5
          60
               1340
                      24765
                              6314
                                     4537
                                             1.95
                                                   70.60
                                                          15.52
                                                                16.18
                                           4.12
19-6
          8
              3743
                      9381
                             6606
                                    2065
                                                 10.37
                                                         7.30
                                                                2.29
19-7
                                             4.97
          52
               4317
                      21349
                             12516
                                      3725
                                                   23.90
                                                         14.00 4.24
19-8
              6726
                      6726
                             6726
                                          7.40
                                                7.40
                                                       7.40
                                                              0.00
                                      0
Total
        279421
                      51357
                               3221
                                      3051
                                             0.00 397.10 6.44 10.19
```

Mode Length Summary

```
----- Distance (meters) ----- Time (minutes) -----
Mode
        Trips Minimum Maximum Average StdDev Minimum Maximum Average StdDev
 1
      138397
                0
                    8460
                            504
                                  600
                                        0.00 141.00
                                                      8.41 10.00
 2
     613101
                   11586
                                         0.00 12.87
                0
                            1650
                                  1133
                                                       1.83
                                                             1.26
 3
      28128
                0
                   7470
                           777
                                  468
                                        0.00
                                             12.45
                                                     1.29
                                                            0.78
 4
       4227
               0
                   7246
                           940
                                 765
                                       0.00
                                             12.07
                                                     1.56
                                                           1.27
 5
              163
                   2969
                           896
                                 427
                                        0.27
                                              4.93
                                                     1.49
                                                           0.71
       113
 7
       9676
               0
                   6573
                           763
                                 396
                                       0.00
                                             10.95
                                                     1.26
                                                           0.66
 8
      30487
                0
                   9633
                           856
                                 673
                                        0.00
                                              16.05
                                                     1.42
                                                            1.12
 9
      12162
                   6380
                                              10.63
                0
                           866
                                  574
                                        0.00
                                                     1.44
                                                            0.96
```

0.00 141.00

2.87

4.89

Alexandria Activity Generator

11586

1377 1117

0

Wed Apr 14 11:01:43 2010 ActGen page 13

Mode Purpose Summary

836291

Total

| Mode- | | I | Distanc | e (meters) | | | Time | e (minute | es) | | |
|---------|-------|------|---------|------------|------|--------|---------|-----------|---------|---------|--------|
| Purpose | Trips | Mini | mum | Maximum | Aver | age St | tdDev N | /Iinimum | Maximum | Average | StdDev |
| | | | | | | | | | | | |
| 1-0 | 27593 | 0 | 6963 | 825 | 478 | 0.00 | 116.05 | 13.75 | 7.97 | | |
| 1-1 | 10320 | 0 | 7881 | 402 | 634 | 0.00 | 131.35 | 6.70 | 10.56 | | |
| 1-2 | 3447 | 0 | 7115 | 728 | 572 | 0.00 | 118.58 | 12.14 | 9.54 | | |
| 1-3 | 2572 | 0 | 4835 | 701 | 495 | 0.00 | 80.58 | 11.69 | 8.25 | | |
| 1-4 | 8308 | 0 | 7985 | 655 | 765 | 0.00 | 133.08 | 10.92 | 12.75 | | |
| 1-5 | 33086 | 0 | 8460 | 239 | 549 | 0.00 | 141.00 | 3.98 | 9.14 | | |
| 1-6 | 745 | 0 | 5452 | 969 | 784 | 0.00 | 90.87 | 16.16 | 13.07 | | |
| 1-7 | 7703 | 0 | 7500 | 445 | 580 | 0.00 | 125.00 | 7.41 | 9.67 | | |
| 1-8 | 1562 | 0 | 5235 | 445 | 591 | 0.00 | 87.25 | 7.41 | 9.85 | | |
| 1-9 | 9351 | 0 | 7494 | 245 | 572 | 0.00 | 124.90 | 4.08 | 9.53 | | |
| 1-11 | 1147 | 0 | 3894 | 1 669 | 461 | 0.00 | 64.90 | 11.15 | 7.69 | | |
| 1-12 | 4756 | 0 | 4320 | 712 | 454 | 0.00 | 72.00 | 11.86 | 7.57 | | |
| 1-13 | 3648 | 0 | 5751 | 727 | 500 | 0.00 | 95.85 | 12.12 | 8.33 | | |
| 1-14 | 9416 | 0 | 5872 | 2 637 | 534 | 0.00 | 97.87 | 10.62 | 8.91 | | |
| 1-15 | 7611 | 0 | 5627 | 7 385 | 528 | 0.00 | 93.78 | 6.42 | 8.80 | | |



```
1-16
        1160
                  0
                      5199
                              792
                                      532
                                            0.00
                                                  86.65
                                                          13.20
                                                                   8.87
1-17
         499
                 0
                      3650
                              714
                                     533
                                            0.00
                                                  60.83
                                                          11.89
                                                                  8.88
1-18
        5357
                  0
                      4357
                              191
                                      383
                                            0.00
                                                  72.62
                                                           3.19
                                                                  6.39
                                                  27.97
1-19
         116
                 0
                      1678
                              668
                                     394
                                            0.00
                                                         11.13
                                                                  6.57
2-0
       214318
                  0
                      11586
                               1612
                                       1070
                                              0.00
                                                     12.87
                                                              1.78
                                                                     1.19
2-1
       54689
                      10261
                                      1159
                                                     11.40
                                                             1.92
                              1732
                                              0.00
                                                                    1.29
                  0
2-2
                              1712
                                      1230
                                                     11.75
                                                             1.89
       21876
                     10579
                                              0.00
                                                                    1.37
                  0
2-3
       19074
                  0
                      10196
                              1735
                                      1199
                                              0.00
                                                    11.32
                                                             1.92
                                                                    1.33
2-4
       17688
                  0
                      9637
                              1665
                                      1214
                                             0.00
                                                    10.70
                                                             1.84
                                                                    1.35
2-5
                      9362
                                      1256
                                             0.00
                                                             1.96
       23046
                  0
                              1768
                                                    10.40
                                                                    1.40
2-6
       33736
                  0
                      9706
                              1627
                                      1210
                                             0.00
                                                    10.78
                                                             1.80
                                                                    1.34
                                                     8.80
2-7
        1727
                105
                       7928
                              1786
                                      1132
                                              0.12
                                                             1.98
                                                                    1.26
2-8
                     10216
                              1699
                                                    11.35
                                                                    1.30
       14544
                                      1170
                                              0.00
                                                             1.88
                  0
2-9
       41150
                     10429
                              1679
                                      1098
                                              0.00
                                                     11.58
                                                             1.86
                                                                    1.22
                  0
                              1713
                                      1216
2-11
        8636
                     10023
                                              0.00
                                                     11.13
                                                             1.90
                                                                    1.35
                  0
2-12
        35218
                  0
                       9380
                              1653
                                      1136
                                              0.00
                                                     10.42
                                                             1.83
                                                                    1.26
2-13
        17631
                  0
                       8856
                              1654
                                      1124
                                              0.00
                                                     9.83
                                                             1.83
                                                                    1.25
2-14
        32396
                  0
                       9940
                              1564
                                      1097
                                              0.00
                                                     11.03
                                                             1.73
                                                                    1.22
2-15
        20434
                  0
                       9761
                              1581
                                      1104
                                              0.00
                                                     10.83
                                                             1.75
                                                                    1.23
2-16
        33661
                  0
                       9083
                              1599
                                      1169
                                              0.00
                                                     10.08
                                                             1.77
                                                                    1.30
2-17
        5045
                      8698
                              1738
                                      1227
                                             0.00
                                                     9.65
                                                            1.92
                                                                   1.36
                  0
2-18
        16552
                  0
                       9188
                              1730
                                      1153
                                              0.00
                                                    10.20
                                                            1.91
                                                                    1.28
                      7858
                              1715
                                      1227
2-19
        1680
                  0
                                             0.00
                                                    8.72
                                                            1.90
                                                                   1.36
                              776
                                      423
3-0
       10770
                  0
                      6143
                                            0.00
                                                   10.23
                                                           1.29
                                                                  0.70
                              784
3-1
        2254
                 34
                      4655
                                      384
                                            0.05
                                                   7.75
                                                           1.30
                                                                  0.64
3-2
        3051
                 0
                     3286
                              711
                                     451
                                            0.00
                                                   5.47
                                                          1.18
                                                                 0.75
3-3
                     7470
                                     600
        379
                 0
                             758
                                           0.00
                                                  12.45
                                                          1.26
                                                                 1.00
3-4
        465
                 0
                     6202
                             856
                                    621
                                           0.00
                                                  10.33
                                                          1.42
                                                                 1.03
3-5
        1057
                     4930
                              869
                                     682
                                           0.00
                                                   8.22
                                                          1.44
                                                                 1.14
                 0
3-6
        617
                 0
                     5632
                             959
                                    809
                                           0.00
                                                  9.38
                                                          1.59
                                                                 1.35
3-7
        227
                 0
                     5681
                             837
                                    608
                                           0.00
                                                  9.47
                                                          1.39
                                                                 1.01
                 0
                                            0.00
                                                   9.38
                                                                 0.92
3-8
        2076
                     5632
                              833
                                     550
                                                          1.38
3-9
        3146
                 0
                     5201
                              776
                                     451
                                            0.00
                                                   8.67
                                                          1.29
                                                                 0.75
3-11
         55
                30
                     1671
                              637
                                     374
                                            0.05
                                                   2.78
                                                          1.05
                                                                 0.62
3-12
         546
                 0
                     3196
                              757
                                     374
                                            0.00
                                                   5.32
                                                          1.25
                                                                 0.62
3-13
                 0
                                                   3.17
         413
                     1900
                              716
                                     353
                                            0.00
                                                          1.19
                                                                 0.59
                     4036
3-14
         663
                 0
                              757
                                     467
                                            0.00
                                                   6.72
                                                          1.25
                                                                 0.78
                 0
                     1945
                                            0.00
                                                   3.23
                                                                 0.59
3-15
         659
                              717
                                     353
                                                          1.19
3-16
         39
                35
                     1651
                              729
                                     446
                                            0.05
                                                   2.75
                                                          1.21
                                                                 0.74
3-17
         86
                76
                      1861
                              698
                                     397
                                            0.12
                                                   3.10
                                                          1.16
                                                                 0.66
                      3644
3-18
        1625
                  0
                              741
                                     406
                                            0.00
                                                   6.07
                                                          1.23
                                                                  0.68
4-0
        1835
                 0
                     5454
                              773
                                     423
                                            0.00
                                                   9.08
                                                          1.28
                                                                 0.70
```

Mode Purpose Summary

| Mode- | - | I | Distance | e (meters |) | | Tim | e (minut | es) | | |
|---------|-------|--------|----------|-----------------|--------|--------|--------|----------|-----------|---------|--------|
| Purpose | Trips | s Mini | mum N | I aximun | ı Aver | age St | dDev 1 | Minimun | n Maximum | Average | StdDev |
| • | - | | | | | | | | | | |
| 4-1 | 865 | 39 | 7246 | 1174 | 1041 | 0.05 | 12.07 | 1.95 | 1.73 | | |
| 4-2 | 59 | 81 | 1915 | 695 | 385 | 0.13 | 3.18 | 1.15 | 0.64 | | |
| 4-3 | 20 | 66 | 1561 | 656 | 430 | 0.10 | 2.60 | 1.09 | 0.72 | | |
| 4-4 | 62 | 112 | 2119 | 773 | 396 | 0.18 | 3.52 | 1.28 | 0.66 | | |
| 4-5 | 333 | 144 | 7246 | 1855 | 1364 | 0.23 | 12.0 | 7 3.08 | 2.27 | | |



| 4-6 15 296 1915 1233 437 0.48 3.18 | 2.05 0.73 |
|---|-----------|
| 4-6 15 296 1915 1233 437 0.48 3.18 4-7 20 252 1747 664 313 0.42 2.90 | 1.10 0.52 |
| 4-8 96 139 1901 772 360 0.22 3.17 | 1.28 0.60 |
| 4-9 646 63 3209 790 397 0.10 5.33 | 1.31 0.66 |
| | 0.91 0.33 |
| 4-12 9 279 1407 742 431 0.45 2.33 | 1.23 0.72 |
| 4-13 19 196 1503 658 436 0.32 2.50 | 1.09 0.73 |
| 4-14 25 449 1580 790 281 0.73 2.63 | 1.31 0.47 |
| 4-15 82 183 1772 750 370 0.30 2.95 | 1.24 0.62 |
| | 0.70 0.00 |
| 4-18 132 185 1907 753 362 0.30 3.17 | 1.25 0.60 |
| 5-0 36 163 2969 1020 544 0.27 4.93 | 1.69 0.90 |
| 5-1 1 328 328 328 0 0.53 0.53 0. | |
| 5-9 76 277 1765 844 347 0.45 2.93 | 1.40 0.58 |
| 7-0 4071 24 3953 763 374 0.03 6.58 | 1.26 0.62 |
| 7-1 145 15 2521 763 387 0.02 4.20 | 1.26 0.65 |
| 7-2 109 24 2587 703 429 0.03 4.30 | 1.16 0.72 |
| 7-3 9 138 1449 660 447 0.22 2.40 | 1.09 0.75 |
| 7-4 661 33 6573 802 555 0.05 10.95 | 1.33 0.93 |
| 7-5 472 0 1924 758 367 0.00 3.20 | 1.26 0.61 |
| | 0.80 0.62 |
| 7-7 323 35 3943 775 424 0.05 6.57 | 1.28 0.71 |
| 7-8 706 103 3953 756 428 0.17 6.58 | 1.25 0.71 |
| 7-9 1613 73 2587 754 358 0.12 4.30 | 1.25 0.60 |
| 7-12 599 94 2506 765 378 0.15 4.17 | 1.27 0.63 |
| 7-13 69 198 1914 811 346 0.32 3.18 | 1.35 0.58 |
| 7-14 542 0 2266 748 360 0.00 3.77 | 1.24 0.60 |
| 7-15 158 0 1876 770 359 0.00 3.12 | 1.28 0.60 |
| 7-16 46 198 3497 1024 827 0.32 5.82 | 1.70 1.38 |
| 7-18 136 8 1815 742 377 0.00 3.02 | 1.23 0.63 |
| | 0.83 0.39 |
| 8-0 12760 0 9633 868 621 0.00 16.05 | 1.44 1.04 |
| 8-1 1014 0 7677 853 809 0.00 12.78 | 1.42 1.35 |
| 8-2 435 0 5669 893 751 0.00 9.43 | 1.48 1.25 |
| 8-3 431 0 7839 1065 1063 0.00 13.05 | 1.77 1.77 |
| 8-4 1630 0 8657 1066 1059 0.00 14.42 | 1.77 1.76 |
| 8-5 1975 0 7677 921 891 0.00 12.78 | 1.53 1.48 |
| 8-6 963 0 8694 830 781 0.00 14.48 | 1.38 1.30 |
| 8-7 1002 0 6453 813 612 0.00 10.75 | 1.35 1.02 |
| 8-8 267 0 4019 597 559 0.00 6.68 | 0.99 0.93 |
| 8-9 1207 35 5701 885 739 0.05 9.50 | 1.47 1.23 |
| 8-11 60 0 2514 765 554 0.00 4.18 | 1.27 0.92 |
| 8-12 670 0 6422 790 570 0.00 10.70 | 1.31 0.95 |
| 8-13 362 34 4931 878 709 0.05 8.22 | 1.46 1.18 |
| 8-14 2291 0 5437 827 555 0.00 9.05 | 1.37 0.92 |
| 8-15 1574 0 5896 804 522 0.00 9.82 | 1.33 0.87 |
| 8-16 439 0 3417 731 426 0.00 5.68 | 1.21 0.71 |
| 8-17 148 94 4332 977 807 0.15 7.22 | 1.62 1.35 |
| 8-18 3207 0 5150 739 380 0.00 8.58 | 1.22 0.63 |
| 8-19 52 39 1493 683 347 0.05 2.48 | 1.13 0.58 |
| 9-0 5075 35 6078 815 461 0.05 10.12 | 1.35 0.77 |
| 9-1 101 188 4284 1832 1020 0.30 7.13 | 3.04 1.70 |



Mode Purpose Summary

| Mode- | - | I | Distance | (meters) |) | | Time | e (minut | es) | | |
|---------|-------|--------|----------|----------|-------|--------|--------|-----------------|-----------|---------|--------|
| Purpose | Trip | s Mini | mum M | [aximum | Aver | age St | dDev N | Ainimu n | n Maximum | Average | StdDev |
| - | - | | | | | | | | | | |
| 9-2 | 19 | 192 | 1562 | 645 | 455 | 0.32 | 2.60 | 1.07 | 0.76 | | |
| 9-3 | 67 | 155 | 6031 | 1575 | 1254 | 0.25 | 10.05 | 2.62 | 2.09 | | |
| 9-4 | 625 | 0 | 6380 | 1208 | 1010 | 0.00 | 10.63 | 2.00 | 1.68 | | |
| 9-5 | 136 | 32 | 4001 | 964 | 661 | 0.05 | 6.67 | 1.60 | 1.10 | | |
| 9-6 | 36 | 82 | 2261 | 765 | 408 | 0.13 | 3.77 | 1.27 | 0.68 | | |
| 9-7 | 5663 | 0 | 6031 | 831 | 515 | 0.00 | 10.05 | 1.38 | 0.86 | | |
| 9-8 | 212 | 128 | 5224 | 850 | 538 | 0.20 | 8.70 | 1.41 | 0.90 | | |
| 9-9 | 1 | 766 | 766 | 766 | 0 1 | .27 1 | .27 1 | .27 0. | .00 | | |
| 9-11 | 101 | 188 | 4284 | 1832 | 1020 | 0.30 | 7.13 | 3.04 | 1.70 | | |
| 9-12 | 17 | 226 | 1500 | 920 | 377 | 0.37 | 2.50 | 1.53 | 0.63 | | |
| 9-14 | 33 | 252 | 2319 | 826 | 479 | 0.42 | 3.85 | 1.37 | 0.80 | | |
| 9-15 | 47 | 336 | 1768 | 887 | 344 | 0.55 | 2.93 | 1.47 | 0.57 | | |
| 9-16 | 19 | 122 | 2854 | 893 | 786 | 0.20 | 4.75 | 1.48 | 1.31 | | |
| 9-17 | 10 | 364 | 1791 | 948 | 717 | 0.60 | 2.98 | 1.57 | 1.19 | | |
| | | | | | | | | | | | |
| Total | 83629 | 1 0 | 11580 | 5 1377 | 7 111 | 17 0.0 | 00 141 | .00 2 | .87 4.89 | | |

Number of Households with Problems = 20587 (26.2%)

Total Number of Problems = 50405

Number of Time Schedule (#2) Problems = 13186 (26.2%)

Number of Vehicle Access (#7) Problems = 472 (0.9%)

Number of Activity Location (#27) Problems = 195 (0.4%)

Number of Vehicle Passenger (#28) Problems = 10613 (21.1%)

Number of Activity Duration (#29) Problems = 2907 (5.8%)

Number of Walk Location (#33) Problems = 18 (0.0%)

Number of Transit Location (#35) Problems = 130 (0.3%)

Number of Person Match (#36) Problems = 22884 (45.4%)

Wed Apr 14 11:01:43 2010 -- Process Complete with 1 Warning (0:00:23)



7 TROUBLESHOOTING

The number of household match problems is significant.

Household match problems are most often caused when relatively few household types are used. As a result, a synthetic household could be matched to a survey household that has very different household characteristics (e.g., number of persons, number of workers, or number of vehicles). This makes it difficult to match the household members by agegroup, work status, and gender.

One solution is to add household types in the script described in Section 4.0. This can be done as long as there are an adequate number of survey responses to support the increased level of specificity. A minimum of 10 survey responses per household type is recommended to minimize response bias.

The number of activity generation and location choice problems is significant.

Problems reported by the ActGen program fall into two general categories: fatal problems and information problems. Fatal problems involve issues that the program cannot resolve on its own and that may require corrections to the survey or household data. Fatal problem households are not saved to the output file.

Information problems involve issues that the program can address, allowing it to continue processing the record. The solution may not always be desirable, and the modeler may choose to make corrections to the survey or household data to reduce the potential distortions generated by the default solution.

Vehicle access and activity location problems are the most frequent type of fatal problems. A vehicle access problem basically means the household was allocated an insufficient number of vehicles to satisfy all of the drivers. One potential solution could be to make a vehicle available for every adult in the household.

Activity location problems suggest that the location choice model may be too restrictive or that too many of the activity location weights are zero. A zero activity location weight designates that the activity location should be excluded from the location choice.

The information problems include vehicle passenger and activity duration problems. A vehicle passenger problem means that there is no driver available to transport the passenger. The default solution is to assign the passenger to a "magic move," which essentially means that someone outside the household drove the passenger to the activity.

Activity duration problems are best addressed by ignoring them. This type of problem is generated when the estimated travel time between the trip origin and the trip destination is longer than the allotted time between activities. If both activities are time constrained, the software cannot shift the activity schedule to provide adequate travel time. Because the travel time is based on a simple distance-based calculation, it may not be very



accurate. When the Router builds the path, it may, however, find that the activity schedule is reasonable after all.

8 FREQUENTLY ASKED QUESTIONS

Why would I ever want to use the default distance-based location choice model?

The distance-based model is at least 10 times faster than a skim-based script model. It requires far less data, and the data take less time to prepare. On the other hand, it does not consider time of day, mode, or path—considerations that will be very important in any detailed study in a complex region. But even in those types of applications, it may be desirable to run the distance-based model to help debug the travel survey. Most travel surveys do not go through the types of logic and internal consistency checks that are required for the activity generator to perform efficiently. For example, drivers and passengers may not be traveling at the same time or going to the same locations. A driver may be expected to pick up a vehicle at a location where it was not previously parked, or a person who used transit to get to work may make a drive subtour at lunch time. A distance-based model can be helpful in identifying and fixing these types of problems.

Is it possible to borrow an activity survey from a different region?

The answer is yes, but only with care. The region should have similar travel options, spatial density, overall congestion levels, demographics and auto ownership characteristics. One option might be to combine surveys from several regions to generate enough samples to support additional household types. This might be important for applications that plan to add new travel modes to the region.

